

NAME

ffproxy.quick — filtering HTTP/HTTPS proxy server quick introduction

DESCRIPTION

ffproxy is a filtering HTTP/HTTPS proxy server. It is able to filter by host, URL, and header. Custom header entries can be filtered and added. It can even drop its privileges and optionally `chroot(2)` to some directory. Logging to `syslog(3)` is supported, as is using another auxiliary proxy server. An HTTP accelerator feature (acting as a front-end to an HTTP server) is included. Contacting IPv6 servers as well as binding to IPv6 is supported and allows transparent IPv6 over IPv4 browsing (and vice versa).

This manual describes how to set up a basic HTTP proxy installation. It is assumed that you already have compiled the program or installed it via port or package.

COPYING FILES

The program comes with default configuration files that contain both examples and suggested entries. You can simply copy them to a directory of your choice. This directory will become the program's working directory.

```
mkdir /var/ffproxy
tar cf - db/ html/ | ( cd /var/ffproxy ; tar xf - )
cp sample.config /var/ffproxy/ffproxy.conf
```

Above example would install all needed files to `/var/ffproxy`, which is `ffproxy`'s default working directory.

SECURING

The proxy now has its own working directory. By default, `ffproxy` does not change UID/GID after start. For security reasons we want to enable it. You have two choices know: Either use existing UID/GID or add custom UID/GID for `ffproxy`. See `adduser(8)` or `useradd(8)`, depending on your system, on how to create new IDs.

Edit `ffproxy.conf` and change the lines containing `uid` and `gid`

```
# change UID and GID
#
# to use, both uid and gid must be set
# (disabled by default)
#uid proxy
#gid proxy
uid _ffproxy
gid _ffproxy
```

In addition to changing UID and GID, `ffproxy` should be executed change-rooted to its working directory. So we change `chroot_dir` and `db_files_path` in the configuration file

```
# change root to (only in connection with uid and gid change)
# (disabled by default)
chroot_dir /var/ffproxy

# path to db/ and html/ directories
# (default: /var/ffproxy)
db_files_path .
```

`db_files_path` must be changed, too, since that is relative to new root. Finally, we copy `/etc/resolv.conf` to `ffproxy`'s home to enable DNS in `chroot` and `chown /var/ffproxy` so the proxy's master process can write its PID file

```
mkdir /var/ffproxy/etc
cp /etc/resolv.conf /var/ffproxy/etc/
chmod 750 /var/ffproxy
chown _ffproxy._ffproxy /var/ffproxy
```

ACCESS TO THE PROXY

By default, nobody is allowed to connect to ffproxy. Let's say, we want to provide LAN users a filtering proxy to shut down malicious content coming from the Internet. So the proxy has to be listening on the local network interface only. We change `bind_ipv4` and `bind_ipv6` appropriately in `ffproxy.conf`

```
bind_ipv4 martyr.burden.eu.org
bind_ipv6 martyr.burden.eu.org
```

Additionally, we have to change `db/access.ip`. By, for example,

```
^192\.168\.10\.
```

we allow 192.168.10.0/24 to use our proxy.

STARTING THE PROXY

Last step is starting ffproxy. Keep in mind that we run the program change-rooted to `/var/ffproxy`, so files are relative to new root.

```
cd /var/ffproxy ; /usr/local/bin/ffproxy -f ffproxy.conf
```

starts ffproxy. Now test if it works correctly. If not, change `ffproxy.conf` and/or read `ffproxy(8)` `ffproxy.conf(5)`

ffproxy is not running as daemon right now. If everything seems to work, simply shut down the proxy by pressing CTRL-C, set 'daemonize yes' in the configuration file and start ffproxy again.

TRANSPARENT OPERATION

The proxy allows transparent operation, that is, HTTP traffic is redirected to the proxy which simulates a HTTP server so that the users don't have to specify a proxy server. Consider forced usage of a proxy server as well. To do that, you will have to configure your NAT accordingly. On OpenBSD you'll want a line like

```
rdr on rl0 proto tcp from any to any port 80 -> 127.0.0.1 port 8080
```

in `/etc/pf.conf`. See your NAT's documentation for details on how to do this.

VERSION

This manual documents ffproxy 1.6 (2005-01-05).

SEE ALSO

`ffproxy(8)`, `ffproxy.conf(5)`, `pf.conf(5)`